

***SonicWALL Server
Anti-Virus***



Activating Your Server Anti-Virus Upgrade

To activate and download your Server Anti-Virus software, you must first register your activation key on the SonicWALL website at the SonicWALL registration site <<http://www.mysonicwall.com>.> Follow the instructions below to activate and download your Server Anti-Virus software.

1. Log into your user account, and select a SonicWALL appliance to activate Server Anti-Virus.

Note: If you have only one SonicWALL appliance, you can use **Quick Register** to activate your Server Anti-Virus Upgrade.

Manage Product

PRO

RENAME

TRANSFER

DELETE

Applicable Services

Service Name	Status	Expiry/Key
1. Content Filter	INSTALLED	19 May 2002
2. VPN Upgrade	INSTALLED	leo-ammo-fin-hugh-bass-wart
3. VPN Client Upgrade	INSTALLED	-
4. Premium Support	ACTIVATE	-
5. Extended Warranty	INSTALLED	19 Apr 2003
6. Authentication Service - Admin	ACTIVATE	-
7. Authentication Service - Client	ACTIVATE	-
8. High Availability	ACTIVATE	-
9. View Point	ACTIVATE	-
10. Anti-Virus Upgrade	ACTIVATE	-
11. Firmware Download	ACTIVATE	-
12. Support 8X5	INSTALLED	18 Jul 2002
13. Support 24X7	ACTIVATE	-
14. Intl Support	ACTIVATE	-
15. Server Anti Virus	ACTIVATE	-

2. Click **Activate** next to **Server Anti-Virus** in the list of **Applicable Services**.
3. Enter the Activation Key from the back of this manual into the **Activation Key** field. Click **Submit**.

SONICWALL COMPREHENSIVE INTERNET SECURITY SOLUTIONS HOME | NEWS | WHERE TO BUY | CONTACT US

My SonicWALL My Products Preferences Personal Info Feedback Tech Support Help

Logged in: testanu456

Activate Service - Total Anti Virus Server

Please enter the activation key:


Activation Key:

SUBMIT CANCEL

mySonicWALL 1.6.37

Copyright 2002 SonicWALL

4. When you click **Submit**, you are directed to the Server Anti-Virus Download Center.



- In the **Server Anti-Virus Software Download** section, click [here](#) to go to the **Available Software** page.

Available Software

Language Preference:

日本国内のお客様へ : VPN Clientをダウンロードをされる場合は、Languageで必ず「Japanese」を選択してください。

Server Anti-Virus

Description	Version	Size	Release Date
GroupShield v5 for Microsoft Exchange 2000	1.0	30000K	Apr 24, 2002
GroupShield v5 for Microsoft Exchange 5.5	1.0	30000K	Apr 24, 2002
NetShield v4.3 for Microsoft Windows	1.0	13000K	Apr 24, 2002

SNMP

Description	Version	Size	Release Date
SW-FIREWALL-TRAP.MIB	2.0.0	13K	Apr 1, 2002
Previous Versions			
SW-SMI.MIB	2.0.0	2K	Apr 1, 2002
Previous Versions			

VPN Client

Description	Version	Size	Release Date
VPN_Client(for Win9x/ME/NT/2000/XP)	8.0	50500K	Mar 27, 2002
Previous Versions			

日本国内では現在VPN Client 8.0 のサポートしておりません。

- Click on one of the software links to download the **Server Anti-Virus** zip file.

Installing GroupShield for Exchange 2000

- Download **GSv5_MSExchange.zip** and unzip it. The zip file contains all of the files listed in the table.
- Unzip **GS52E2KE.zip** and use the executable file to install GroupShield.
- Download and install latest SuperDAT file. See the **Configuration Tips** section for information on SuperDAT files.

- Set **AutoUpdate** feature in **GroupShield** to automatically download new DAT files.

Contents of GSv5_for_MSEExchange2000.zip

Language	File Name	Version	Application	Notes
English	GS52E2KE.zip 27MB	5.2.0	Win 2000	Installation Software
English	Readme.tif 157KB	5.2.0	Win 2000	Release Notes
English	GSE52KIG.pdf 1.18MB	5.2.0	Win 2000	Installation Guide
English	gse52cgs.pdf 643KB	5.2.0	Win 2000	Configuration Guide
English	gse52kpg.pdf 2.9MB	5.2.0	Win 2000	Product Guide

Installing GroupShield for Exchange 5.5

- Download **GSv5_for_MSEExchange55.zip** unzip it. The zip file contains all of the files listed in the table.
- Unzip **GS5E55EN.zip** and use the executable file to install GroupShield.
- Download and install latest SuperDAT file. See the **Configuration Tips** section for information on SuperDAT files.
- Set **AutoUpdate** feature in **GroupShield** to automatically download new DAT files.

Contents of GSv5_for_MSEExchange55.zip

Language	File Name	Version	Application	Notes
English	GS5E55EN.zip 25.7MB	5.0.0	Win NT, Win 2000	Installation Software
English	Readme.txt 105KB	5.0.0	Win NT, Win 2000	Release Notes
English	gse50E55ig.pdf 1.3MB	5.0.0	Win NT, Win 2000	Installation Guide
English	gse50E55wcg.pdf 756KB	5.0.0	Win NT Win 2000	Configuration Guide
English	gse50E55wpg.pdf 2.9MB	5.0.0	Win NT, Win 2000	Product Guide
English	GS5E55_Cluster.rtf 75KB	5.0.0	Win NT, Win 2000	Cluster Installation Tech Note

Installing NetShield for Windows

1. Download **NSv43_for_MSWindows.zip** and unzip it. The zip file contains all of the files listed in the table.
2. Unzip **NNT450LEN.zip** and use the executable file to install NetShield.
3. Unzip **nnt45sp1.zip** and use the executable to install Service Pack 1. Reboot the computer.
4. Download and install the latest SuperDAT files. See the **Configuration Tips** section for information on SuperDAT files.
5. Set **AutoUpdate** feature in **GroupShield** to automatically download new DAT files.

Contents of NSv43_for_MSWindows.zip

Language	File Name	Version	Application	Notes
English	Readme.txt 59KB	4.5.0	Win NT, Win 2000	Release Notes
English	NNT450LEN.zip 8.8MB	4.5.0	Win NT, Win 2000	Updates Engine to 4.1.6.0 (DAT version 4183)
English	nnt45sp1.zip 3.44MB	4.5.0	Win NT, Win 2000	Service Pack 1
English	Readme.txt 58KB	4.5.0	Win NT, Win 2000	Release Notes for Engine Update to 4.1.6.0
English	nnt45wgs.pdf 793KB	4.5.0	Win NT, Win 2000	Getting Started Guide
English	nnt450wag.pdf 2.5MB	4.5.0	Win NT, Win 2000	Administrator's Guide
English	readme.txt 40KB	4.5.0	Win NT, Win 2000	Service Pack 1 Release Notes

Configuration Tips

Upgrading with SuperDAT Files

After installing GroupShield or NetShield, go to <http://www.nai.com> and locate the Anti-Virus Updates link. Follow the link to the latest SuperDAT files. SuperDAT files contain (Engine + DAT) in the hyperlinked description. The SuperDat file needs to be downloaded and installed immediately after either the GroupShield or NetShield installation, and then updated regularly as new Anti-Virus engines are released. Check the website monthly for updates.

Updating DAT Files

You can configure the Autoupdate feature of GroupShield and NetShield to automatically download the latest DAT files daily (recommended). Alternatively, the DAT file should be manually downloaded daily/weekly from <http://www.nai.com>, and then installed onto the server(s) running GroupShield or NetShield. The DAT file contains the latest virus definition information. Always check that the latest DAT file version is running on your server(s) for maximum anti-virus protection.

Product Documentation

If the file names listed in the tables do not match the file names on the download site, download the latest Server Anti-Virus Upgrade manual at <http://www.sonicwall.com/products/documentation.html>.

The product documentation associated with GroupShield or NetShield is included in the zip file and you should refer to it for complete installation instructions and configuration information.

Anti-Virus Activation Key



SonicWALL, Inc.
1160 Bordeaux Drive
Sunnyvale, CA 94089-1209
Phone: 408-745-9600
Fax: 408-745-9300
E-mail: sales@sonicwall.com
Web: <http://www.sonicwall.com>

Part # 232-000317-00
Rev A. 05/02